



DATE MEASUREMENTS TAKEN

Participant Details

Name:	<input type="text"/>		
Date of Birth:	<input type="text"/>	<input type="checkbox"/> Male	<input type="checkbox"/> Female
Diagnosis/ Disability:	<input type="text"/>		
NDIS Number:	<input type="text"/>	<input type="checkbox"/> Self Managed	<input type="checkbox"/> Plan Managed
		<input type="checkbox"/> NDIA Managed	
Plan Manager invoice email:	<input type="text"/>		

Contact Details

Parent Name:	<input type="text"/>
Phone Number:	<input type="text"/>
Email:	<input type="text"/>
Address:	<input type="text"/>

Details of prescribing Allied Health Professional

Name:	<input type="text"/>
Allied Health Profession :	<input type="text"/>
Organisation :	<input type="text"/>
Email :	<input type="text"/>
Delivery Address (if different to address in contact details):	<input type="text"/>

Ready-To-Wear Hensinger Collar

This form is used to place an order for a ready-to-wear Hensinger Collar. Complete pages 1 and 2 of the form and return via email. Please be aware that ready-to-wear standard Hensinger collars are returnable only if in new condition and subject to approval.

Signature (if submitted via email this is taken as an electronic agreement to this declaration)

By submitting this form, I agree that I, as a registered health professional, have assessed the client and prescribed the Hensinger collar with the specifications in this order with due diligence and care and that the collar is returnable only if in new condition and subject to approval.

Name: _____ Signed: _____




Ready-To-Wear Hensinger Collar

Ready-to-wear Hensinger collars are available in 4 standard sizes and two variations, low back and high back. The low back option wraps around the neck, while the high back version offers increased support under the base of the head (occiput) due to its more prominent back profile.

For accurate measurements ensure the head and neck is in supported in a midline alignment and breathing, swallowing and vision functions are maintained or improved.

1. Measure the neck circumference (A) and round to the nearest 1 cm.
2. Measure vertically between the top of the shoulder and the bottom of the ear lobe and round off the nearest 1 cm. Then subtract 1.2 cm to allow for ear clearance and head movement (B).
3. Compare these measurements with the dimensions listed in the size chart provided below.

Size	A: Inner circumference of collar (measure neck circumference)	B: Height of collar (measure from earlobe to shoulder, minus 1.2cm)
Extra Small	22.8cm (9")	2.5cm (1")
Small	30.5cm (12")	3.8cm (1.5")
Medium	35.5cm (14")	5.0cm (2")
Large	40.5cm (16")	6.3cm (2.5")



When an individual's neck circumference falls between two sizes, the circumference of a standard collar may be reduced using the 7635 Linear Cushion. These padded cushions come in two thickness options, 6mm and 12mm, and can be trimmed and secured inside the collar to reduce the circumference. The 6mm may reduce circumference up to 2.5cm, and the 12mm may reduce the circumference up to 5.0cm.

Ready-To-Wear Hensinger Collar Order:

Hensinger Type: ☐ Low back ☐ High back

Hensinger Size : ☐ Extra Small ☐ Small ☐ Medium ☐ Large

Linear Cushion (if required) : ☐ 6mm ☐ 12mm